

How to Rent Hash and Mine Placeholder




Placeholder is mined using the Sha256 algorithm. This is the same algorithm used to mine bitcoin. ASICS (hardware designed specifically to mine bitcoin) dominate this algorithm, meaning the average user with a CPU or GPU cannot realistically create enough hash to compete.

Fortunately, since there is so much hashpower available for Sha256, it is relatively inexpensive to rent.

There are two mainstream options for renting hashrate for Placeholder. This guide will instruct you in the use of both NiceHash and Mining Rig Rentals



niceHASH



MININGRIGRENTALS.COM



niceHASH

Navigate to <http://www.nicehash.com>

Live marketplace Find miner Latest payments Language: English

About For sellers For buyers Help **Register / Login**

Largest Crypto-Mining Marketplace

Sell or buy computing power on demand

SELL

computing power of your PC, server, workstation, ASIC or farm

- Get paid in Bitcoins
- Payments from 0.001 Bitcoin
- Payments from once per day
- No registration required
- Free software & user friendly guides

[Learn more](#) [Download](#)


BUY

massive hashing power for mining Bitcoin, Zcash, Ethereum and other coins


- Minimum order price 0.005 Bitcoin
- Cancel at any time without a cancellation fee
- Pay only for valid shares
- Mine on any pool you want
- Real-time statistics & dashboard

[Learn more](#) or [register now](#)


Register a new account or login with an existing account



Send bitcoin (a minimum of 0.005 BTC) to your nicehash wallet



While waiting for your bitcoin to transfer, setup the Placeholder pool in nicehash.



Add new pool Your chosen pool must use the defined or higher pool difficulty.

CUSTOM POOL NAME: Placeholder

ALGORITHM: SHA256

MINIMAL POOL DIFFICULTY: ≥ 1000000

STRATUM HOSTNAME OR IP: stratum+tcp:// 104.248.177.232

PORT: 3256

USERNAME: FGdmA7Ex44PGxodRPicaoLXCumJE72faAf

PASSWORD: x

Test your pool to verify whether your pool is compatible. [Read more](#)

Test pool Close **Add pool**

Fill out the pool information as follows:

Custom Pool Name: Placeholder

Algorithm: SHA256

Stratum Hostname or IP: 104.248.177.232

Port: 3256

Username: Your Placeholder Address

Password: x

niceHASH Dashboard For buyers For sellers Wallet Settings Support Help Logout

My pools search + Add new pool

My orders
My pools
Marketplace

Pool name	Algorithm	Stratum	Port	Username	Password	
Placeholder	SHA256	104.248.177.232	3256	FGdmA7Ex44PGxodRPica...	x	Remove Check Edit

Navigate to the nicehash Marketplace

